

Email Plug-In

Email Plug-In Manual for Centrafuse™

Author: Flux Media

Version: Tested with Centrafuse 1.13

Date: May 17, 2007



About

This is an email reader plug-in for Centrafuse. You can enter your email account settings and your email will be displayed and read aloud. You can also view and send a quick reply using the built-in quick-reply templates. *Note: This plug-in uses an internet connection to check and download your email. If you're using a wireless account for internet access, ensure you have an appropriate data plan before installing this plug-in.*

Installation of the plug-in

Open the file CFEmail.msi and follow the instructions. When prompted for the install path be sure to enter the path of the Centrafuse install folder and not any subfolder or any other folder. For example, "C:\Program Files\Flux Media\Centrafuse".


Installation (cont'd)

From the Settings menu, select BUTTON LAYOUT, press SETUP and you will see the screen below. Press up/down to locate the button that you want to assign to Email. Select the button and press SET.



Choose a button, press SET

Now you will see the Select Action screen. Press up/down until you locate the EMAIL action. Select it as the action for the selected button and click OK. Once it is set, select CLOSE to return to the Centrafuse Settings menu. Click CLOSE again to exit Settings.



Assign Email plug-in as the Action to the selected button.


Setup

Use the arrows to navigate left or right until the SETTINGS button is shown. Press the SETTINGS button.



SETTINGS button in Centrafuse™

In Settings, press up/down to locate EMAIL. Select it, and press SETUP.



Choose EMAIL plug-in in Centrafuse™ settings.

This will open the Setup screen for the Email plug-in. Here you can change the display name for the plug-in, and enter your email account settings such your name, your email address, and your username (usually same as email address).

EMAIL PAGE 1/4

DISPLAY NAME AUTO DIAL

EMAIL NAME

EMAIL ADDRESS

USER NAME

Setup (continued)

EMAIL PAGE 2/4

PASSWORD

INCOMING SERVER
pop3.mailserve.net

OUTGOING SERVER
mail.mailserve.net

MINUTES TO CHECK EMAIL
30

◀ ▶ SAVE CANCEL

Setup Page 2 for Email plug-in

Email account settings are continued on page 2 of settings. Here you enter your email account, password, the name of your incoming mail server, outgoing mail server and the interval at which to check for new messages, in minutes.

EMAIL PAGE 3/4

DAYS TO KEEP
30

INCOMING PORT
110

OUTGOING PORT
25


SERVER TYPE
POP3

◀ ▶ SAVE CANCEL

Setup Page 3 for Email plug-in

Email account settings are continued on page 3. Here you can change the default number of days to keep email. The next two settings are Incoming Port and Outgoing Port which correspond to the Incoming and Outgoing mail servers, respectively, found on page 2. The last setting is for the server type of the incoming mail server. You can choose between IMAP and POP3. Choosing IMAP will adjust the default mail server ports to the default IMAP ports, and vice-versa for POP3.

Setup (continued)



EMAIL PAGE 4/4

IMAP FOLDER
Inbox

INCOMING SECURITY
None

OUTGOING SECURITY
None

◀ ▶ SAVE CANCEL

Setup Page 4 for Email plug-in

IMAP Folder

On page 4 of Email settings, you will find the rest of the Email settings. IMAP Folder is the folder where your mail is set to arrive on the IMAP server. This is usually "Inbox" unless it's been changed.

Security

The options for Incoming and Outgoing Security settings are regarding the type of security which is implemented on the mail server for remote connections. This usually will not have to be changed, unless you are experiencing problems receiving your email. For example, Google's Gmail requires "SSL/TLS Implicit" for the both the incoming and outgoing server to function properly. Some office or work email servers use mode "SSL/TLS Explicit" when connecting.

Usage

You should see this button in Centrafuse main menu. Press it to open Email.




EMAIL button in Centrafuse™



- When you open Email, the left side shows a page of emails displayed from newest to oldest as shown above.
- Use the up/down arrows on the bottom right to scroll through all your past messages.
- To hear a message read aloud through the speakers, highlight a message and hit the Read button on the top right. This can be pressed again to stop the reading of the message.

Usage (continued)




- To view a particular message, simply touch the message and then it will be displayed in a window which has scrolling buttons and a Reply button as shown above. Hit Close to exit the dialog window.



- To send a quick response, use the Quick Reply feature by hitting yes after prompted to use the Quick Reply List. This will bring up the Quick Reply list. Choose an appropriate response and hit Send.
- If you choose No to Quick Reply, you will be given a keyboard to type your reply into manually.

Usage (continued)



- When an email has been sent, the Email plug-in will alert you with an "Email Sent" message as shown below.

